

Seqrite Endpoint Security 7.6 Administrator's Guide

วิธีการเปิดใช้งาน Roaming

SEPS SME SEPS Business SEPS Total SEPS Enterprise Suit

<u>วิธีการเปิดใช้งาน Roaming</u>

ฟีเจอร์ Roaming คือการที่ทำให้เครื่อง Client สามารถรับส่งข้อมูลกับเครื่อง Seqrite EPS Server ได้ แม้ จะไม่ได้อยู่ในเครือข่ายเดียวกัน แต่เครื่องต้องออกเน็ตได้ เป็น Cloud Platform

1. เข้าสู่หน้า Console Seqrite Endpoint Security Management

ไปที่ Admin Setting > Clients > Roaming Clients > Connect to cloud platform

?							
In this section, you can set EPS clients as roaming. This feature will let the clients update their status, download latest configuration from the EPS Server via Cloud based Roaming Service even when the clients are outside your organizational network and connected through integrated							
ic							

> OK

?

- > Enable Roaming Service
- > Roaming Mode
 - Automatic ทุกเครื่องเป็น Roaming ได้
 - Manual เลือกเฉพาะเครื่อง
- > Apply

		Welcome Administrator	🔅 Admi	in Settings	🥲 Support	? Help	🔁 Lo	gout
Seqrite Endpoint Security 7.6 Enterprise Suite			Home	Clients	Settings	Reports	1	
Admin Settings								?
Server Clients								
Client Installation Inactive Client Asset Management Roaming Clients Data Loss Prevention	Roaming Clients In this section, you can set EPS from the EPS Server via Cloud to through Internet. Common EPS Server via Cloud to through Internet. Common EPS client Common Manual In this mode, only selected [Select Clients] Apply	clients as roaming. This feature w based Roaming Service even wher t can connect to Roaming Service I clients can connect to Roaming S	ill let the clie 1 the clients a automaticall jervice.	ents update th are outside yo	ieir status, dow our organizatior	nload latest co ial network and	nfiguratio 1 connecte	n ≵d